

Edge 2 Software Release, Version 4.4.3



New

- Ventilation based on CO2 and/or some functionality with NH3 levels: Added a CO2 compensation ventilation to the base CFM, using a hysteresis.
- Persist report data for room sensors: Report data for room sensors will now be saved and retained.

Improvements

- Update Edge 2 default values: Default values for Edge 2 have been updated.
- CO2 alarm now is triggered when changing settings to below current levels.
- Display "-" in reports empty cells.
- Pre-opening with variable fans.
- Do not log invalid values for reports.

Bug Fixes

- Missing data on the reports: Display missing days in report as a row of empty cells.
- Fans transition from stage 2 to stage 1.

Item	Description
EDG2-MC-RETRO	Edge 2, Main Controller Retro

Please contact your District Manager if you have any questions.